


Installing LD2.4 Drivers on Windows 7


To install the USB drivers for an LD2.4 device under Windows 7, follow the instructions below:
Connect the device to a spare USB port on your PC.

Windows 7 will search any suitable driver for the device.


If no suitable driver is automatically found then the following procedure should be followed.
Press the Windows start button to bring up the start menu and select "Control Panel".




From the Control Panel window select Device Manager:



In the Device Manager window there will be a device under Other Devices with a yellow warning symbol to indicate a problem or no driver installed.




Right click on Other devices -> Montarbo USBNet to open up the system menu, where you must select the “Update Driver Software...” option. In the new pop-up menu select to manual search for a driver (Browse my computer for driver software).





Select the second option to browse manually.

In the address box write-down the exact location in which the driver is located or has been previously copied. This may be a CD or any specific folder on the PC . The location shown in the screenshot is only an example: the driver could have been saved in any user-chosen location.




After entering the address select “NEXT” to start the installation. The warning can be ignored and you can continue installation by selecting “Install this driver software anyway”.






When the installation has finished a completion screen is displayed.



Click Close to close this window and go back to the Device Manager window.



The Device Manager will now report a new entry under Universal Serial Bus Controllers This is indicated in the above screenshot as the Montarbo USBNet.